


Animate a Name Cards



Animate the letters of your name,
initials, or favorite word.



Animate a Name Cards

Try these cards in any order:

- **Color Clicker**
- **Spin**
- **Play a Sound**
- **Dancing Letter**
- **Change Size**
- **Press a Key**
- **Glide Around**

Color Clicker

Make a letter change color
when you click it.



Color Clicker

scratch.mit.edu




GET READY



Choose a letter from the Sprite Library.




Choose a backdrop.



To see just the letter sprites, click the **Letters** category at the top of the Sprite Library.

ADD THIS CODE



Try different numbers.

TRY IT

Click your letter.



Spin



Make a letter turn when you click it.






GET READY



Go to the
Sprite Library.



Click the **Letters** category.



Choose a letter sprite.

ADD THIS CODE



Try different
numbers.

TRY IT

Click your letter.



TIP

Click this block to reset the sprite's direction.



Play a Sound



Click a letter to play a sound.



Play a Sound


scratch.mit.edu



GET READY



Go to the
Sprite Library.




Click the **Letters** category.



Choose a letter sprite.



Choose a backdrop.



Click the **Sounds** tab.



Choose a sound.

ADD THIS CODE




Click the **Code** tab.



Choose a sound
from the menu.


TRY IT

Click your letter.



Dancing Letter

Make a letter move to the beat.



Dancing Letter

scratch.mit.edu



GET READY



Choose a backdrop.



Stage



Choose a letter from the Sprite Library.



Click the **Extensions** button (at the bottom left).



Then click **Music** to add the music blocks.

ADD THIS CODE


```
when this sprite clicked
  move 10 steps
  play drum (1) Snare Drum for 0.25 beats
  move -10 steps
  play drum (6) Closed Hi-Hat for 0.25 beats
```

Type a minus sign to move backward.

Choose a different drum from the menu.

TRY IT

Click your letter.



Change Size

Make a letter get bigger and then smaller.

A small, stylized orange letter 'E' with a black outline and a white mouse cursor arrow pointing at its bottom-right corner.A large, stylized orange letter 'E' with a black outline, centered in the frame.A medium-sized, stylized orange letter 'E' with a black outline, centered in the frame.A large, stylized orange letter 'E' with a black outline, centered in the frame.

Change Size

scratch.mit.edu



GET READY



Go to the
Sprite Library.



Click the **Letters** category.



Choose a letter sprite.

ADD THIS CODE

```
when this sprite clicked
  repeat 15
    change size by 10
  repeat 15
    change size by -10
```

Type a minus sign
to get smaller.


TRY IT

Click your letter.



TIP


Click this block to reset the size.



Press a Key



Press a key to make your letter change.



Press a Key


scratch.mit.edu



GET READY



Choose a backdrop.



Choose a letter from the Sprite Library.




ADD THIS CODE



Try different numbers.

TRY IT



Press the **space** key.

TIP



You can choose a different key from the menu. Then press that key!

Glide Around

Make a letter glide smoothly
from place to place.



Glide Around

scratch.mit.edu

GET READY




Choose a backdrop.



Choose a letter from the Sprite Library.



ADD THIS CODE




Try different numbers.

TRY IT

Click your letter to start.



TIP



When you move a sprite, you can see the numbers for **x** and **y** update.

x is the position from left to right.

y is the position up and down.